DUO PLUS YARN

"WENDY" TOP





Size: S - M - L

Materials: Adriafil Duo Plus (45) 6-6-7 balls,

size 3 1/2 knitting needles

Gauge: 23 sts and 31 rows in Stockinette st = 10x10 cm. Take time to check gauge and switch needles if necessary.

Stitches:

1x1 Ribbing: alternately K1 and P1.

Stockinette st: on right side, knit; on wrong side, purl.

Cable pattern worked over 20 sts: work following chart. White square = knit, x = purl, transfer 3 sts to 1st cable needle, hold in front. transfer the next 2 sts to a 2nd cable needle, hold in back, K3; P2 from 2nd cable needle, K3 from 1st cable needle, = transfer 3 sts to 1st cable needle, hold in back, transfer the next 2 sts to a 2nd cable needle, hold in back, K3; P2 from 2nd cable needle, K3 from 1st cable needle.

Directions:

Back: Cast on 98-108-118 sts and work 28 cm in 1x1 Ribbing. Continue working in Stockinette st. Armhole shaping: when work measures 42 cm bind off 1 time 3, 1-2-2 times 2 and 5 times 1 st at both edges, every 2 rows. Now decrease 0-2-6 times 1 st at both edges, every 4 rows. Neckline shaping: when work measures 50-51-52 cm bind off the center 20-22-24 sts and finish each half separately. At neck edge continue binding off 1 time 3, 2 times 2 and 8 times 1 st, every 2 rows. Shoulders: when work measures 60-61-62 cm bind off the rem 14 sts.

Front: Cast on 104-114-124 sts and set up stitch pattern as follows: 42-47-52 sts in 1x1 Ribbing, 20 sts in Cable pattern, 42-47-52 sts in 1x1 Ribbing. When work measures 28 cm, transfer the first 42-47-52 sts to a cable needle or waste yarn, continue working cable pattern and work in Stockinette st over the last 42-47-52 sts. When work measures 35 cm, decrease 32-33-34 times 1 st, every 2 rows. Decrease as follows: work cable pattern, slip the next st, K1 and PSSO. Armhole shaping: decrease same as back. Bind off cable sts at the same length as back, making sure to work 6 times 2 sts tog. Work sts from cable needle or waste yarn in Stockinette st and cast 18 extra sts onto needle at end of row. From now on work these 18 sts in 1x1 Ribbing, until front is finished. At neck edge decrease 32-33-34 times 1 st, alternately every 2 and 4 rows. Decrease as follows: work to the last 2 sts before 1x1 Ribbing section, K2 tog, 18 sts in 1x1 Ribbing. Bind off sts at the same length as back.

Finishing: Pick up 73-77-81 sts along back neck and work 1 row in 1x1 Ribbing. Bind off in 1x1 Ribbing. Sew the cast-on sts from left front behind right front cable. Sew shoulder seams. Pick up 94-102-110 sts along armholes and work 1 row in 1x1 Ribbing. Bind off in 1x1 Ribbing. Sew shoulder seams.



